

# PinPoint III – Software Update Guide

⚡ Use this procedure to load the latest PinPoint III Hub software. Total update time: ~10 minutes (iPhone) or ~6 minutes (Android).

---

<b>Step 1: Power Up →</b>	Power up the PinPoint 3 system.
<b>Step 2: Open App →</b>	Open the Capstan App on your phone.
<b>Step 3: Select PinPoint →</b>	From the main screen, tap <i>PinPoint</i> .
<b>Step 4: Navigate to Update Tab →</b>	Go to the <i>Update</i> tab (bottom right icon).
<b>Step 5: Connect to Hub →</b>	Tap the Capstan logo (upper right) and connect to Hub.
<b>Step 6: Open File Browser →</b>	Tap the green folder icon.
<b>Step 7: Check for Updates →</b>	Tap <i>Check Files on Server</i> ; latest files auto-download.
<b>Step 8: Select File →</b>	Tap software to download to device
<b>Step 9: Send to Controller →</b>	Tap file again → choose <i>Send to Controller</i> .
<b>Step 10: Upload →</b>	Wait for transfer (~10 min iPhone / ~6 min Android).
<b>Step 11: Power Cycle →</b>	Power off tractor, trip PinPoint breaker, wait 30s, power back on. Software loads automatically.
<b>Step 12: Verify Revision →</b>	From Home, select Heartbeat icon → confirm correct software revision is displayed.
<b>Step 13: Continue →</b>	Proceed with standard setup procedures.

---

✓ **Software Update Complete**